

Wrap Side Tie Midi Skirt




INSTRUCTION

BOOKLET

Table of Contents

- 3 What do I need to start sewing?
- 4 Printing instructions
- 6 Size chart
- 7 Patterns
- 8 Sewing instructions
- 17 Glossary



COPYRIGHT - All rights reserved.
© Patterns For Less

Written permission is required to copy and/or distribute copies of this document, whether or not it is for profit. Photocopying, digitizing or copying this document to share is strictly prohibited.

Help support the development of Patterns For Less sewing patterns by checking out the [bestsellers](#) and [new arrivals](#).

Sign up to my email list for discounts and exciting store updates!


PatternsForLess.com

For inquiries, questions, drop me a message on

IG: [PatternsForLess](#)
info@patternsforless.com

Please reach out to us if you have any questions about the sewing pattern or step by step instructions, we are happy to help!


What do I need to start sewing?



Sewing machine
Overlock/Serger
Pattern printout
Sewing thread
Measuring tape
Water erasable pen/Chalks
Scissors
Ruler
Pins



Hook and eye
8" or 20.3cm long invisible zipper
1 1/8" or 2.9cm width elastic band



Our favorite sewing supplies!

2 yard x 60" width viscose linen fabric

Fabric Recommendations: polyester, linen, cotton, rayon challis, crepe, gauze, viscose.

Check out all the fabric options we love!

Testing a sewing pattern with muslin fabric is important because:

Muslin is inexpensive and allows you to adjust the fit before using costly fabric. It helps you see how the pattern pieces work together and make necessary changes. You can practice techniques and construction methods. It's a low-risk way to experiment with design modifications. Muslin saves money by preventing costly mistakes with your final fabric.

In essence, it helps ensure your final garment fits well and turns out as expected.

Printing Instructions

Let's print out the pattern!


The sewing pattern comes with 3 different printing options! The US Letter and A4 print is a tile version PDF that you can print out at home. The A0 version is used by a printshop to print on a single sheet of paper and saves time taping the separate pages together.

Additionally, you can use view mode to only select/print the size you are working on. Each pattern file is designed with layers of different sizes. There is an option to print only your size or all sizes based on your preference. Open the file in Adobe Acrobat and keep in legend layer.


If you print at home, then you need to trim each sheet by cutting off the top and excess margin. Tape each page together by row, and then attach the rows together. Use the diamond marks to align everything!

Always make sure to print on 100% scale.
(Do not 'fit to page' or reduce the size!)


There is a test square on the first page of the pattern.
Use as a scale to check if the dimensions are 5x5cm and/or 2x2".



A4



US Letter



Size Chart

inches

SIZE	BUST	WAIST	HIP
XS	30	25	36
S	33	27	38
M	36	29	40
L	39	31	42
XL	41	33	44
XXL	44	35	46
XXXL	47	37	48

centimeters


SIZE	BUST	WAIST	HIP
XS	76	63	91
S	84	68	96
M	91	74	102
L	99	79	107
XL	104	84	112
XXL	112	89	117
XXXL	119	94	122

FINISHED GARMENT MEASUREMENT

SIZE	LENGTH	WAIST	HIP
XS	35 3/8" 90 CM	24 3/4" 63 CM	37 3/8" 95 CM
S	35 3/4" 91 CM	26 3/8" 67 CM	39" 99 CM
M	36 1/8" 92 CM	28" 71 CM	40 6/8" 103 CM
L	36 3/4" 93.5 CM	30" 77 CM	42 7/8" 109 CM
XL	37 3/8" 95 CM	32 6/8" 83 CM	45 1/4" 115 CM
XXL	38" 96.5 CM	35" 89 CM	47 6/8" 121 CM
XXXL	38 6/8" 98 CM	37 3/8" 95 CM	50" 127 CM

* This data was obtained from manually measuring the product, it may be off by 1-2cm

Patterns




Wrap side tie midi skirt pattern pieces include:

- A- Front Right Skirt, cut 1
- B- Front Left Skirt, cut 1
- C- Back Skirt, cut 1 on folded fabric
- D- Front Waist Facing, cut 1
- E- Back Waistband, cut 1
- F- Right Side Tie, cut 1
- G- Left Side Tie, cut 1



$\frac{3}{8}$ " or 1cm seam allowance is already included unless indicated on the pattern or instruction book.

Sewing Instructions






Step 1- Follow the notches on the Front Right Skirt (A) and create 2 pleats. Ensure the pleat folds are facing toward the hem. Baste stitch along the sides to secure the pleats in place.

Step 2- Double fold the waist opening of the Front Right Skirt (A) $\frac{1}{4}$ " or 0.6cm and topstitch.




Step 3- Cut out the dart from the paper pattern and layover on the wrong side of the Front Left Skirt (B). Mark the dart legs and dart point using chalk or water erasable pen.


Step 4- Sew the darts from point to dart leg without backstitching. Finish the ends by hand tying with double knots. Press the darts toward the side seam.




Step 5- Double fold the center front curved line of the Front Left Skirt (B) 1/4" or 0.6cm and topstitch.




Step 6- Overlock stitch the hem of Front Right Skirt (A), Front Left Skirt (B), and Back Skirt (C). Fold $\frac{7}{8}$ " or 2.2cm width and then $\frac{3}{4}$ " or 1.9cm width topstitch.




Step 7- Fold the Back Waistband (E) in half lengthwise wrong side together and press.



Step 8- Slide 1" or 2.5cm width elastic in between the folded Back Waistband (E). Topstitch 1/4" or 0.6cm width, then stretch the elastic so it meets the other end of Back Waistband (E) and 1/4" or 0.6cm width topstitch to secure.





Step 9- Place the Back Waistband (E) and Back Skirt (C) right side together. Sew along the waist 3/8" or 1cm width straight stitch. Overlock stitch the seam allowance and press the seam toward the hem.




Step 10- Fold the Right Side Tie (F) in half right side together and straight stitch $\frac{1}{4}$ " or 0.6cm width. Turn the Right Side Tie (F) right side out and press.


Step 11- Place the Right Side Tie (F) and Front Right Skirt (A) right side together. Ensure the Right Side Tie (F) is located where the pleats are. Baste stitch to secure the Right Side Tie (F) in place.




Step 12- Overlock stitch along the center front opening of Front Right Skirt (A). Fold $\frac{3}{8}$ " or 1cm width toward the wrong side of fabric and $\frac{1}{4}$ " or 0.6cm width straight stitch from top to hem.



Step 13- On the wrong side of Front Waist Facing (D), apply a fusible interfacing with light steam iron. Overlock stitch the hem on Front Waist Facing (D).



Step 14- Place the Front Waist Facing (D) and Front Left Skirt (B) right side together and sew along the waist opening with $\frac{3}{8}$ " or 1cm width straight stitch. Press the Front Waist Facing (D) open and closely edge topstitch along the Front Waist Facing (D). Then, fold the Front Waist Facing (D) toward the wrong side of Front Left Skirt (B) and press.





Step 15- Fold the Left Side Tie (G) in half right side together and straight stitch $\frac{1}{4}$ " or 0.6cm width. Turn the Left Side Tie (G) right side out and press.





Step 16- Place the Left Side Tie (G) and Front Left Skirt (B) right side together. Ensure the Left Side Tie (F) is located on wearer's left side seam. Baste stitch to secure the Left Side Tie (G) in place.

Step 17- Stack Front Right Skirt (A) and Front Left Skirt (B) pieces on top of each other so the wrong side of Front Right Skirt (A) is touching the right side of Front Left Skirt (B). Baste stitch on wearer's right side seam.




Step 18- Place Front Skirt (A&B) and Back Skirt (C) right side together and close the wearer's left side seam with $\frac{3}{8}$ " or 1cm straight stitch. Overlock stitch the seam allowance and press the seam facing toward the Back Skirt (C).



[illegible]

15 WRAP SIDE TIE MIDI SKIRT

Hook & Eye



Step 21- Hand sew the hook and eye at the starting point of the zipper on the wrong side of the Front Skirt (A&B) and Back Waistband (E).




Enjoy The Skirt !

Step 22- Gently press all around and enjoy your wrap side tie midi skirt!



Sewing Glossary

Back Stitch




When you start a new seam or finish the seam, always backstitch by hitting the reverse button on your sewing machine. Back stitching consists of 3-4 stitches to lock the stitching and prevent unraveling.

Bias Tape



Bias tape is widely used in neckline, spaghetti strap, and other garment finishings. Prepare the bias strap by cutting in half diagonally to give a nice stretch. When needing to make a long continuous bias tape, sew the diagonal pieces together as long as you need.


Buttonholes



There are various styles of buttonholes you can create with your sewing machine. For cleaner look, add interfacing and sew over the buttonhole more than once to create nice tight holes.


Use a buttonhole foot by inserting the button in the back of the foot, and snap the foot into place. Pull the button hole lever down, and select the buttonhole stitch on your machine. Press the pedal and stitch away, your machine will automatically go through the steps to make an accurate buttonhole.

Edge Stitch



Edge stitches are typically used to decorate or emphasize the original seam line. To achieve clean edge stitch, use a special footer to sew close to the edges without gliding off. Sew slowly to control the fabric.


Flat Felled Seam



Flat felled seam or jeans seams is a great way to sew heavy duty fabric or bottoms to strengthen the garment.

Sew the fabric right sides facing each other. Trim one of the seam allowances in half. Turn the raw edge under and fold over to hide the half cut edge. Topstitch down the enclosed seam allowance.

French Seam



When sewing silk or chiffon with delicate fabrication, French seams are a great way to achieve an excellent quality finish.


Place wrong sides of fabric facing each other and sew $\frac{1}{4}$ " or 0.6cm. Press the seam and fold the fabric along the seam line. Enclose the seam by stitching $\frac{1}{4}$ " or 0.6cm from the folded edge.

Hand Basting




Basting or running stitches are simple hand stitches to use instead of pinning or gathering. Alternatively, you can increase the stitch length and loosen tension on your sewing machine to create a basting look.

Open Seam



Open seams are a technique used to make the seams clean and flat. It can be used for CF, CB, or side seams. Overlock both raw edges first, and then stitch the 2 pieces together to iron the seam open.


Overlock



Overlock stitches help to bind raw cut edges to prevent from fraying. This technique is mostly accomplished by overlock machine, serger, or your home sewing machine with overlock stitch setting.

Overlock machines have 2 to 3 needles and 2 top threads and lower threads to braid and stitch, which results in a variation of blanket stitch. The knife blade cuts the fabric edge to give a clean overlock stitch.


Pivoting



Use the pivoting method when sewing corners or at an angle such as pocket corners, tip of collars, v-neckline, etc.


Execute the technique by leaving the needle in the fabric, lift the footer, and then turn the fabric as much as you need. Continue to sew by lowering the footer again, then stitch in the new direction.

Pressing



Steam and iron with pressure after every stitch you make in the garment. Pressing helps to relax the threads and finish the seams cleanly. Be aware to avoid extreme steam on natural fabrics such as cotton and linen due to the risk in shrinkage.


Right side - Wrong side



All fabrics have a right side and wrong side. The right side is mostly worn visibly to the outside whereas the wrong side should be on the inside of the garment. Some fabrics are easy to identify the right or wrong side by sheen or texture, but some might look identical both right and wrong side.

To find out the right and wrong side of the fabric, look for little pinholes along the selvage. The clean side of the holes is the right side.



Seam Allowance



The seam allowance or SA is the extra fabric next to the stitch line all around each pattern piece. The additional space allows us to sew everything together.


Depending on the seams and styles, the seam allowance is usually ($\frac{1}{4}"$, $\frac{3}{8}"$, $\frac{1}{2}"$) or (.6cm, 1cm or 1.2cm) width. Always refer to the pattern and instruction booklet for accurate seam allowance amount.

Topstitch



The purpose of top stitches are to add strength to the garment. Iron the seam allowance to the side. Straight stitch $\frac{1}{8}$ " or 0.3cm, or $\frac{1}{4}$ " or 0.6cm away from the original seam to sew the right side and seam allowance together.

Twin Needle



Twin needles are used in knit casual or sportswear for clean finishing without needing a double fold hemming method. The 2 top threads and 1 bobbin thread create parallel topstitch on the right side of the fabric and zigzag stitch on the wrong side of the fabric.